

15437-0592

1/16




Fig. 1

15437-0592

2/16




Fig. 2A





Fig. 2B

15437-0592

4/16




*Fig. 3A*


15437-0592

+

5/16



*Fig. 3B*




*Fig. 3C*

+

15437-0592

6/16




*Fig. 3D*

15437-0592

+

7/16




*Fig. 3E*

+

15437-0592

8/16




*Fig. 3F*



15437-0592

9/16



*Fig. 3G*

15437-0592

10/16

global#	zoneadm list -cv	402			
401	ID NAME	403	STATE	405	PATH
0	global		running		/
-	my-zone		configured		/aux0/my-zone
-	fun		installed		/aux0/fun
15	nofun		ready		/aux1/nofun
7	lucky		running		/aux0/lucky
13	unlucky		shutting_down		/aux1/unlucky
global#	pgrep -ff zoneadm	420			
10819	zoneadm -z nofun	422			
10227	zoneadm -z lucky	424			
10304	zoneadm -z unlucky	426			

Fig. 4A

+

11/16

```
global# zonecfg -z my-zone ↗430
zonecfg: my-zone> create ↗432
zonecfg: my-zone> set zonepath=/aux0/my-zone ↗434
zonecfg: my-zone> add net ↗436
zonecfg: my-zone:net> set physical=hme0 ↗438
zonecfg: my-zone:net> set address=129. 146. 126. 203/24 ↗440
zonecfg: my-zone:net> end ↗441
zonecf: my-zone> verify ↗442
zonecfg: my-zone> commit ↗444
zonecfg: my-zone> ^D
global#
```

*Fig. 4B*

+

15437-0592

+

12/16

global# zoneadm -z my-zone verify 446  
/aux0/my-zone must not be world readable.  
cannot verify zonepath /aux0/my-zone because of the above errors. 448  
zoneadm: zone my-zone failed to verify  
global# chmod 700 /aux0/my-zone 450

global# zoneadm -z my-zone verify 452  
global# zoneadm -z my-zone install 454

global# zoneadm list -iv 456  

ID NAME	STATE	PATH
0 global	running	/
- my-zone	installed	/aux0/my-zone 458

Fig. 4C

+

15437-0592

+

13/16

global# zoneadm -z my-zone ready ↗<sup>460</sup>

global# zoneadm list -v ↗<sup>462</sup>

ID	NAME	STATE	PATH
0	global	running	/
1	my-zone	ready	/aux0/my-zone

↗<sup>464</sup>

Fig. 4D

global# zoneadm -z my-zone boot ↗<sup>466</sup>

global# zoneadm list -v ↗<sup>468</sup>

ID	NAME	STATE	PATH
0	global	running	/
1	my-zone	running	/aux0/my-zone

↗<sup>470</sup>

Fig. 4E

+

15437-0592

global# zoneadm list -v <sup>472</sup>			PATH <sup>474</sup>	
ID	NAME	STATE	/	
0	global	running	/aux0/my-zone	
1	my-zone	running		

global# zoneadm -z my-zone halt <sup>476</sup>			PATH <sup>480</sup>	
ID	NAME	STATE	/	
0	global	running	/aux0/my-zone	
-	my-zone	installed		

global# zoneadm list -iv <sup>478</sup>				
ID	NAME	STATE		
0	global	running		
-	my-zone	installed		

Fig. 4F

15437-0592




Fig. 4G

15437-0592

16/16




Fig. 5